


Configuring Indicators

- [Introduction](#)
- [Step 1 - Edit the properties file](#)
- [Step 2 - Apply configuration changes](#)
- [Step 3 - Generate a new snapshot - optional](#)

 **Summary:** this page describes how to configure the Indicators feature.

Introduction

The Indicator feature provides a **set of indicators** for a given snapshot - see [Application - Overview](#) for more detailed information. These indicators are designed to provide basic information quickly so that the snapshot can be validated. The following indicators can currently be configured to be displayed on completion of a snapshot:

- Artifacts in transactions
- Complete Transactions with only end point
- Data entities used by transactions
- Incomplete transactions
- Part of functional enhancement
- Programs/Classes in transactions
- TF/DF weight ratio
- Delivery related indicators
- etc.

This feature is **enabled** "out-of-the-box" in **1.20.x** releases of AIP Console. If you need to **disable** it, this requires a modification to the AIP Node **properties** file. See instructions below.

Step 1 - Edit the properties file

The configuration file (**aip-node-app.properties**) is available in **EACH AIP Node**, therefore if you have more than one AIP Node, you will need to modify the configuration file on each node where you want to configure the Indicator feature:

```
%PROGRAMDATA%\AipConsole\AipNode\aip-node-app.properties
```

Locate the following lines in the file and change to **true (to enable)** or **false (to disable)** as required:

```
# =====  
# set to true if you want to enable the checks of snapshot  
# -----  
snapshot.indicator.check.enabled=false
```

Save the file when you have completed the changes.

Step 2 - Apply configuration changes

Restart the AIP Node to ensure all changes are taken into account:

- If the AIP Node is installed as a **Windows Service**, restart the service
- If the AIP Node is running only using the **batch file**, close the CMD window to stop the process, then restart then using the following file:

```
%PROGRAMFILES%\AipConsole\AipNode\tools\runAIPConsole.bat
```

Step 3 - Generate a new snapshot - optional

If you are enabling the feature, you will need to generate a new snapshot to view the Indicators in [Application - Overview](#).